

Common Commands for the iSeries

Command	What it does?
CHGJOB (press f4)	Change your jobs attributes
CHGJOB prtdev(PRT02)	Change your current job to print on printer PRT02
DSPJOB	Display your current job information
DSPJOBLOG	Display your current job's command and message history
DSPMSG	Display message associated with your user sign-on
DSPMSG QSYSOPR	Display messages associated with the SYSTEM OPERATOR
DSPSYSSTS	Display System statistics – percent of system disk(ASP) used
DSPTAP	Display the information on your tape
DSPTAP data(*SAVRST)	Display Information from tape (List ALL files)
INZTAP newvol(SAVT01) density(*DEVTYPE)	Initialize the tape YOU MUST include a New Volume Id.(user choice) YOU MUST include tape density (*MLR3 for example)
GO PROBLEM	Work with Existing Hardware problems
PRTDEVADR	Print a listing of Device, port and addresses for a controller
WRKSPLF	Show your spool files.
WRKWTR	Work with ALL printers
WRKOUTQ *ALL	Work with ALL user Print queues
WRKOUTQ QEZJOBLOG	Work with output queue that records print outs of expired jobs due to errors.
WRKSYSVAL QDATE	Tape option “2” and change SYSTEM date – ALL iSeries user ARE affected
WRKSYSVAL QTIME	Take option “2” and change SYSTEM time – ALL AS/400 users ARE affected
WRKDEVD *ALL	Work with ALL devices (check status of terminal/PC)
WRKDEVD PRT*	Work with devices that begin with PRT like PRT01, PRT02, etc
WRKCFGSTS *CTL	Status of Controllers
WRKCFGSTS *LIN	Status of Lines
WRKJOBQ QBATCH	List jobs waiting in batch mode to go to active status.
WRKACTJOB	View Active jobs both batch and interactive – BE VERY CAREFULL
WRKACTJOB sbs(QBATCH)	Work with Batch Jobs currently running
WRKACTJOB sbs(QINTER)	Work with Interactive Jobs currently running
WRKUSRJOB	Display your job names and status