

Obtaining Your System's Information

The following instructions will enable you to obtain Version/Release, Feature Code, Model and Serial Number for your AS/400.

OS/400 Release Level

To obtain the OS/400 version/release level that you are running, (for example, V4R4M0), enter the command:

DSPPTF

```
Display PTF Status                                     System:  BARS01
Product ID . . . . . : 5769999
IPL source . . . . . : ##MACH#B
Release of base option . . . . . : V4R4M0 L00

Type options, press Enter.
 5=Display PTF details  6=Print cover letter  8=Display cover letter

  Opt  PTF ID      Status              IPL Action
  --  -
  -   TL00147  Temporarily applied  None
  -   TL00049  Permanently applied  None
  -   TL99313  Superseded           None
  -   TL99230  Superseded           None
  -   TL99229  Superseded           None
  -   TL99166  Superseded           None
  -   TL99117  Superseded           None
  -   TL99082  Superseded           None
  -   RE99352  Permanently applied  None

More...
F3=Exit  F11=Display alternate view  F17=Position to  F12=Cancel
```

On the third line down is displayed the text 'Release of base option', next to which is the version, release and modification level of OS/400.

Obtaining Your System's Information

AS/400 Model Number

The "model number" is determined by entering the following command on a command line:

```
DSPSYSVAL QMODEL
```

```
Display System Value
System value . . . . . : QMODEL
Description . . . . . : System model number

Model number . . . . . : 170

Press Enter to continue.
F3=Exit  F12=Cancel
```

AS/400 Feature Code

The method to determine the "processor feature code" depends on which release of OS/400 you are currently running. If you are at V4R3M0 or later, then enter the following command:

```
DSPSYSVAL QPRCFEAT
```

```
Display System Value
System value . . . . . : QPRCFEAT
Description . . . . . : Processor feature

Processor feature . . . : 2290

Press Enter to continue.
F3=Exit  F12=Cancel
```

Obtaining Your System's Information

AS/400 Serial Number

The "serial number" is determined by entering the following command on a command line:

```
DSPSYSVAL QSRLNBR
```

```
Display System Value
System value . . . . . : QSRLNBR
Description . . . . . : System serial number

Serial number . . . . . : 10488AM

Press Enter to continue.
F3=Exit  F12=Cancel
```